



ALMPRO

Installation with .msi



Oude Oeverstraat 120-4
6811 JZ
Arnhem
The Netherlands

t: +31(0) 88 1221 800
f: +31(0) 88 1221 899
www.rsconnect.net
info@rsconnect.net

Introduction

This guide will explain how to install ALMPRO using the .msi wrapper.

The .msi installation wrapper is available for download via our Customer Service Center portal.

Follow the steps below to download the file and use it to install ALMPRO.

Installation

Follow the procedure below.

1. Logon to <https://www.rsconnect.net/en/support/>
2. Then click on the software section in the left-hand menu.
3. You can find the .msi at the bottom of the right-hand screen:
4. Download and place the .msi in the same folder as the alm_v6.exe.
5. Optionally add license and configuration settings in the same folder (only when changed, otherwise the current license and settings will be preserved). The installation folder will contain:
 - o alm_v6.exe (application) – required
 - o alm_v6.msi (installer) – required
 - o almmodule.lic (license) – optional
 - o almsettings.txt (configuration) – optional
6. Then execute alm_v6.msi to deploy.

Menu	Software	
> Algemene gegevens		
> Contractgegevens		
> Documenten		
> Software		
> Licenties		
> Contact opnemen		
	Download latest software	
Bestandsnaam	Versie	Notitie
ALM4 software and license upgrade instructions.pdf	ALM4 software and license upgrade instructions	ALM 4
alm4.zip	ALM 4 v4.5r48 expires 1-Feb-2020	Please use license file to activate or run as evaluation
ALM_v6.exe	ALM 6 v6r0.1 expires 9-mrt-2026	Please use ALM 6 license file to activate or run as evaluation
ALM PRO software and license upgrade instructions.pdf	ALM4 software and license upgrade instructions	ALM PRO 5
ALM_v5.exe	ALM 5 v5r6.3 expires 13-mar-2025	Please use ALM 5 license file to activate or run as evaluation
alm_v6.msi	alm_v6.msi	MSI installer (wrapper) to be used with ALM_v6.exe

Additional Information

For additional information please contact or visit:

- United Kingdom: +44 203 608 8259
- Other countries: +31 88 1221 800
- <http://www.rsconnect.net>
- support@rsconnect.net